Subject: Setting up Renrem
Posted by JPNOD on Thu, 30 Mar 2006 20:06:20 GMT

View Forum Message <> Reply to Message

Hey,

Can anyone explain me on how to setup Renrem. I tried it before but I could not get it to work. And since I would like to use it now.

Renegade Remote Server Management Tool
Version 1.11 - ST 7/25/2002 3:20PM
Usage: RenRem.exe <options> ip port password [local_port]

Options: -r=Request - Send the specified request to the server then quit
Bad parameters''
I tried: 83.203.123.xx 123password 40Xx

Can anyone show me a example on how to add it into the shortcut.

Thanks in advance,

Subject: Re: Setting up Renrem
Posted by light on Thu, 30 Mar 2006 22:11:14 GMT

View Forum Message <> Reply to Message

I believe this is what you need:

RenRem.exe 127.0.0.1 7000 pass123

(127.0.0.1 is localhost, so the server has to be on the same machine as you are running RenRem on. Port can be any unused port from 1 to 25500 or something like that.)

Where 7000 = your Remote Admin port in Server.ini

; RemoteAdminPort =
;
; The port to connect to for remote administration.
; This can be set per slave. The default slave ports will be shown when
; connecting to the master with the RenRem tool.

RemoteAdminPort =7000

and pass123 = RemoteAdminPassword

; RemoteAdminPassword =
;
; This is the password required to connect to a server with the RenRem
; admin too.
; Slave servers inherit this setting from the master.

RemoteAdminPassword =pass123

and remoteadmin is allowed:

; AllowRemoteAdmin =
;
; Set this to true to enable remote server administration via the RenRem
; tool. You must also set a password for remote administration to be
; allowed.
; Slave servers inherit this setting from the master.

AllowRemoteAdmin =True

I hope that works. I'm going on my assumptions. I use WinRem, so i'm not 100% sure.

Subject: Re: Setting up Renrem
Posted by Hex on Thu, 30 Mar 2006 22:57:06 GMT
View Forum Message <> Reply to Message

Use renrem32