

---

Subject: Brenbot.cfg Question

Posted by [Buggy](#) on Wed, 22 Dec 2004 08:04:28 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

How can i enable the bot that he works as WolSpy. I want not to use WolSpy but i want to see the Server on GameSpy. I have a Wol Server! With WolSpy he works fine, but WolSpy always crashes, i want to enable WolSpy on the Bot, ich have installed Core Patch 1.2 with ssaow and Brenbot

brenbot.cfg

Start Configuration-IRC-----

# Edit the information below for your setup.

# At least edit BotName and IrcChannel.

BotName = cncxp2

BotFullName = BlazeRegulator/BRenBot

IrcServer = irc.euirc.net

IrcPort = 6669

IrcChannel = #cnc-xp

#---Q/NickServ-----

# Enable auth via "Q" or "NickServ" below. Sample input is shown.

Qauth = 0

Qusername = RenBot01

Qpassword = mypassword

# Note for NickServ auth you give the name of nickserv and the full ident string as example

Nickservauth = 1

Nickservname = Nickserv

Nickservauth = identify RenBot01 mypassword

#--Windows or Linux-----

# BotMode MUST be "WIN32" for windows servers, or "LFDS" for Linux servers.

BotMode = WIN32

#--Remote Admin Settings-----

# The next 3 lines should be the same info that is in your server.ini

# Note: Although it says "Linux" its the same for Win32

RenRemLinuxHost = 81.169.137.171

RenRemLinuxPort = 4853

RenRemLinuxPassword = \*\*\*\*\*

#--FDS Installation-----

# Verify these paths are correct with your Renegade installation.

# Note: FDSLogFilePath must end with the trailing slash (as example below)!!

# Note: Linux users use forward slashes (/) in your paths.

FDSConfigFile = D:\Renegade\Server\data\svrcfg\_cnc.ini

FDSLogFilePath = D:\Renegade\Server\

#--Miscellaneous Settings-----

# Every x minutes the bot will announce a random line from AutoAnnounceFile.

AutoAnnounceInterval = 60

# LadderLookup currently not working. Do not turn it on or it will hang the bot.

EnableLadderLookup = 1

# Set this to 0 or anything but 1 to disable voting.

VotingEnabled = 1

# How long people get to place votes. Default here is 60 seconds.

VotingPeriod = 60

# Set vehicle kick to 1 for Sniper servers

VehicleKick = 0

#--BR Configuration Files-----

# BR Config Files - You shouldn't have to change these names. You can still open them with notepad.

AutoAnnounceFile = autoannounce.brf

Messagesfile = messages.brf

AdminsFile = admins.brf

MastersFile = masters.brf

KickLogFile = kicklog.brf

BanLogfile = banlog.brf

Generate\_GameSpy\_Queries = 1

# Generate independant gamespy queries, instead of quering the original GSA UDP Query handler. In WOL Mode, you don't have one.

GameSpyQueryPort = 23500

# The query handler listens on this port

Broadcast\_Server\_To\_GameSpy = 1

# Broadcast the query handler to gamespy.

# If you enable this, YOU NEED TO SET "GameSpyQueryPort=<value>" in server.ini to 0!!!!

# BRENBOT WILL BEHAVE BADLY IF YOU DO NOT DO THIS!

# Gamelog / Donate Settings

# Donate is tied to gamelog, because bhs.dll causes to crash the fds, when a player

# tries to donate to a player, which has not loaded the game yet. with gamelog, brenbot

# can find out, if a player has loaded the map. you can disable it here.  
# BEWARE! PEOPLE WILL BE ABLE TO CRASH YOUR SERVER!

Seperate\_Donate\_From\_Gamelog = 1

# Delete gamelog files instead of archiving it. Normally, brenbot archives it.

# Delete\_Gamelog\_Files = 1

#--End Configuration-----

---

---

Subject: Brenbot.cfg Question

Posted by [zunnie](#) on Wed, 22 Dec 2004 09:49:06 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

GameSpy\_IP = IPhere

enter that in the gamespy area config in brenbot.cfg

---

---

Subject: I NEED HELP! FROM YOU IF IT WORKS ON WOL!

Posted by [Dave Anderson](#) on Sun, 26 Dec 2004 23:44:28 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

COULD YOU WRITE A COPY OF YOUR BRENBOT.CFG FOR ME? I CANT GET MINE TO WORK! AND COULD YOU TELL ME WHAT NEEDS TO BE CHANGED FOR MINE TO WORK? I WOULD DEEPLY APPRECIATE THIS.

---

---

Subject: Brenbot.cfg Question

Posted by [zunnie](#) on Mon, 27 Dec 2004 19:50:31 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

RenRemLinuxHost = 81.169.137.171

should be:

RenRemLinuxHost = 127.0.0.1

---

---

Subject: Brenbot.cfg Question

Posted by [serenitie](#) on Tue, 04 Jan 2005 21:11:28 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

zunnieRenRemLinuxHost = 81.169.137.171

---

should be:

RenRemLinuxHost = 127.0.0.1

I tried that and the bot shutdown :s

---

---

Subject: Brenbot.cfg Question

Posted by [zunnie](#) on Thu, 06 Jan 2005 05:44:58 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Run it through the command prompt and note the errors.

startmenu > run > cmd [enter]

goto brenbot dir, execute it.

---