

---

Subject: Co-op FDS not working

Posted by [Kioshin18](#) on Tue, 27 Nov 2007 00:29:04 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Sorry for the double post guys. But Thanks for the helpful tips about BRenbot.

I now have BRenbot setup and talking with my IRC server. Everything seemed to be working well. But when I open up my FDS exe to make a server I get what you see in the screen shot.

Dose anyone know what this means? It works fine without BRenbot. In fact I actualy coppied my entire Renegade FDS folder before installing BRenbot in case something went wrong, and when I replace it with the backup of before Brenbot it has no trouble making the server. So is BRenbot not talking to my FDS?

Keep in mind that I am running the Co-op Beta 2.25, so I don't know if that has anything to do with it.

Thanks again

---

**File Attachments**

1) [untitled.bmp](#), downloaded 252 times

---

---

---

Subject: Re: Co-op FDS not working

Posted by [Matix101](#) on Tue, 27 Nov 2007 00:49:15 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

danpual is a fucking noob and when you install BR, he forgot to make the installer make a file.

In your FDS directory (inside /Server/) make a folder called

"log" and inside that folder make a folder called "biatch" and inside that folder create a text file under the name of "main.txt"

---

Knp

---

---

Subject: Re: Co-op FDS not working

Posted by [Genesis2001](#) on Tue, 27 Nov 2007 00:59:02 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Matix101 wrote on Mon, 26 November 2007 17:49danpual is a fucking noob and when you install BR, he forgot to make the installer make a file.

In your FDS directory (inside /Server/) make a folder called

"log" and inside that folder make a folder called "biatch" and inside that folder create a text file under the name of "main.txt"

Knp

Don't post complaints about a good program...

Anyway, on topic...

@Kioshin18: make sure that you have set up the RemoteAdmin stuff in brenbot.cfg and server.ini. (Make sure they're the same...) If they are already, then I don't know what the problem is... :\

~MathK1LL

---

---

Subject: Re: Co-op FDS not working

Posted by [Kioshin18](#) on Tue, 27 Nov 2007 02:24:06 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Matix101 wrote on Mon, 26 November 2007 18:49danpual is a fucking noob and when you install BR, he forgot to make the installer make a file.

In your FDS directory (inside /Server/) make a folder called

"log" and inside that folder make a folder called "biatch" and inside that folder create a text file under the name of "main.txt"

Knp

I did exactly what you said and while it no longer shows that error, the FDS just exist upon loading. In the screen shot it looks all good and well but shortly after just exits/crashes.

I have made sure all the information is the same between both the server.ini and the BRenbot.ini.

Server.ini

AllowRemoteAdmin = true

RemoteAdminPassword = Not for you to know

RemoteAdminIP = 127.0.0.1

RemoteAdminPort = 4949

BRenbot.ini

RenRemLinuxHost = 127.0.0.1

RenRemLinuxPort = 4949

RenRemLinuxPassword = Not for you to know

I saw somewhere to leave the IP blank, but when I did that BRenbot complained

---

### File Attachments

1) [untitled2.bmp](#), downloaded 222 times

---

---

Subject: Re: Co-op FDS not working

Posted by [Matix101](#) on Tue, 27 Nov 2007 03:16:43 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

If it crashes, it means you need to reinstall your co-op mod. Why? If you installed BR over the Co-Op mod, the installation of BR gets rid of the necessary files you had earlier from the co-op mod, and that's why it crashes.

Reinstall the co-op mod and it should work. Save your server.ini and your svr\_conf.ini before re-installing it so you save time after you reinstall the mod.

---

---

Subject: Re: Co-op FDS not working

Posted by [Matix101](#) on Tue, 27 Nov 2007 03:18:31 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

MathK1LL wrote on Mon, 26 November 2007 18:59Matix101 wrote on Mon, 26 November 2007 17:49danpual is a fucking noob and when you install BR, he forgot to make the installer make a file.

In your FDS directory (inside /Server/) make a folder called

"log" and inside that folder make a folder called "batch" and inside that folder create a text file under the name of "main.txt"

Knp

Don't post complaints about a good program...

Anyway, on topic...

@Kioshin18: make sure that you have set up the RemoteAdmin stuff in brenbot.cfg and server.ini. (Make sure they're the same...) If they are already, then I don't know what the problem is... :\

~MathK1LL

My reply was quite helpful and more "on-topic" then yours.

And I never complained about BR, I find it excellent. I find danpaul a nubcake for making his installer have quite a few problems.

Like when you install BR, brloader keeps updating the same shit, cause of a certain file mishap or whatever, and then IPBot trying to connect to the database but it says "invalid password"

It only adds up.

---

---

---

---

Subject: Re: Co-op FDS not working

Posted by [Ethenal](#) on Tue, 27 Nov 2007 03:41:52 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

And saying "nubcake" makes you cool.

---

---

---

---

Subject: Re: Co-op FDS not working

Posted by [Goztow](#) on Tue, 27 Nov 2007 08:22:26 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Matix, go back to DOS'ing, k tx?

---

---

As said: if it works before installing brenbot, then try to install renegadefds, then install brenbot and then install the co-op mod.

---

---

---

---

Subject: Re: Co-op FDS not working

Posted by [danpaul88](#) on Tue, 27 Nov 2007 11:02:27 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Matix101 wrote on Tue, 27 November 2007 03:18And I never complained about BR, I find it excellent. I find danpaul a nubcake for making his installer have quite a few problems.

---

---

Like when you install BR, brloader keeps updating the same shit, cause of a certain file mishap or whatever, and then IPBot trying to connect to the database but it says "invalid password"

Two things:

- 1: I didn't miss any files from the installer, it installs BIATCH exactly the same as the zip file from BlackIntel does, so if there's something missing it was also missing from the zip file when I downloaded it from their website.
- 2: Did you actually GET a password for the IPDB? If not then that's why you get invalid password messages. Also that's only on versions of the IPDB plugin that were released AFTER that installer was made, hence why it updates to that version.

---

---

**Subject: Re: Co-op FDS not working**

Posted by [Matix101](#) on Tue, 27 Nov 2007 12:19:40 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Goztow wrote on Tue, 27 November 2007 02:22Matix, go back to DOS'ing, k tx?

As said: if it works before installing brenbot, then try to install renegadefds, then install brenbot and then install the co-op mod.

Get back to fixing UDP flooding, k tx?

Idiot.

---