

---

Subject: !setnextmap / !maplist || Strange problem  
Posted by [zunnie](#) on Sat, 27 Mar 2004 00:02:45 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

```
#--Start Configuration-IRC-----
# Edit the information below for your setup.
# At least edit BotName and IrcChannel.
BotName = SoQServBot
BotFullName = SoQServBot
IrcServer = irc.black-cell.net
IrcPort = 6667
IrcChannel = #zunnieserv
#---Q/NickServ-----
# Enable auth via "Q" or "NickServ" below. Sample input is shown.
Qauth = 0
Qusername = RenBot01
Qpassword = mypassword
# Note for NickServ auth you give the name of nickserv and the full ident string as example
NickServAuth = 1
NickServName = NickServ
NickServAuth = identify TheCorrectPass
#--Windows or Linux-----
# BotMode MUST be "WIN32" for windows servers, or "LFDS" for Linux servers.
BotMode = WIN32
#--Remote Admin Settings-----
# The next 3 lines should be the same info that is in your server.ini
# Note: Although it says "Linux" its the same for Win32 :-)
RenRemLinuxHost = 127.0.0.1
RenRemLinuxPort = 4848
RenRemLinuxPassword = rempaswd
#--FDS Installation-----
# Verify these paths are correct with your Renegade installation.
# Note: FDSLogFilePath must end with the trailing slash (as example below)!!
# Note: Linux users use forward slashes (/) in your paths.
FDSConfigFile = G:\Westwood\FDS\Server\Data\fanmaps.ini
FDSLogFilePath = G:\Westwood\FDS\Server\
#--Miscellaneous Settings-----
# Every x minutes the bot will announce a random line from AutoAnnounceFile.
AutoAnnounceInterval = 120
# LadderLookup currently not working. Do not turn it on or it will hang the bot.
EnableLadderLookup = 0
# Set this to 0 or anything but 1 to disable voting.
VotingEnabled = 0
# How long people get to place votes. Default here is 60 seconds.
VotingPeriod = 60
# Set vehicle kick to 1 for Sniper servers
VehicleKick = 0
```

```
#--BR Configuration Files-----  
# BR Config Files - You shouldn't have to change these names. You can still open them with  
notepad.  
AutoAnnounceFile = autoannounce.brf  
Messagesfile = messages.brf  
AdminsFile = admins.brf  
MastersFile = masters.brf  
KickLogFile = kicklog.brf  
BanLogfile = banlog.brf  
#--End Configuration-----
```

Everything is set the way its supposed to be, it seems almost as if im the only who has this problem. (along with a few others, but most dont have this problem somehow)

Its also very unlikely that its my firewall causing this because i disabled both of them (Zonealarm Pro and the windows internal one) temporarily, but this didnt fix the problem. Could it be the name of the config file? I havent checked that yet, maybe it should be default name (svcfg\_cnc.ini) ?? (ill try that later)

[zunnie]

---