Subject: JTeKGuard Anthrax 1.1.6 instructions Posted by SS217 on Wed, 23 Jun 2004 16:55:32 GMT View Forum Message <> Reply to Message

For those that got into the JTeKGuard beta tomorrow connect to irc.black-cell.net and PM SS saying you are ready, along with the email address you sent the beta letter with, I will email you the link. For those wondering you can still signup for the beta. Just visit http://gloryfades.black-cell.net/home.php

Warning: Please do not run more than one copy of JG on the same computer for the beta.

Warning: Do NOT keep more that one BCServ_Forward.exe open at ANY given time.

Warning: This copy of JG was NOT designed to work with GameSpy.

There will be 4 files you need to edit.

ARotate.ini The file that contains the messages to be repeated every so and so seconds.

Format: number=message (ex. 1=Visit our website http://blah blah blah 2=Rules for <serv> are: <rules> (<serv> and <rules> are variables replaced with real data by the bot))

BCServ_Forward_settings.ini Edit the LogDir to your RenegadeFDS server directory (default C:/westwood/renegadefds/server/)

maprules.ini

Used for the !maprules command, if there are no specific rules don't add the map into the ini Format:

Map.mix=rules/msgs

(ex.

C&C_Field.mix=No tunnel beacons. No B2B.

C&C_Islands.mix=No B2B.

C&C_Mesa.mix=No B2B. No wall jumping.

C&C_Hourglass.mix=No glitching Obelisk or camping on hill with MRLS and ART.

C&C_Canyon.mix=No tunnel beacons or beacons on roof.

)

JG.ini Main JG config file

[GameOptions] Rules=Server rules used for !rules (public) Welcomemsg=Welcome message when a player joins [FDSSettings] FDSDirectory=C:\Westwood\RenegadeFDS\Server\ FDSSvrCfg=C:\Westwood\RenegadeFDS\Server\Data\svrcfg cnc.ini [KickOptions] KickTime=time to auto-kick player if he was !kick'ed (in seconds) [TbanOptions] TbanTime=time to auto-kick player if he was !tban'ed (in seconds) [IRCOptions] NickServ=Yes (Does this IRC server have NickServ? Please keep the servers on Black-Cell or n00bstories, JG hasn't been tested on another IRCd other than UnrealIRCd) NickPassword=test (If yes, the nickserv password here) IRCNick=JTeKBot (IRC Nickname) IRCServ=irc.black-cell.net (IRC server to connect to on start) IRCChannel=#iteksvrs (IRC channel to log to) IRCAdminChannel=#jteksvr06-admin (IRC admin channel, report major events etc here) OpsAllowedmsg=true (Are ops allowed to use !msg? true / false) HopsAllowedmsg=true (Are halfops allowed to use !msg? true / false) VoiceAllowedmsg=true (Are voices allowed to use !msg? true / false)

Page 2 of 2 ---- Generated from Command and Conquer: Renegade Official Forums