

---

Subject: How do you Change nod and gdi color text ?  
Posted by [DeathC200](#) on Wed, 25 Feb 2009 23:57:16 GMT  
[View Forum Message](#) <> [Reply to Message](#)

Guys i am wondering how do you change the nod and gdi color text can some one please tell me how i am getting very tired of the red and yellow scheme that i have been using for years :/ .

---

---

---

Subject: Re: How do you Change nod and gdi color text ?  
Posted by [Gen\\_Blacky](#) on Thu, 26 Feb 2009 00:14:40 GMT  
[View Forum Message](#) <> [Reply to Message](#)

hud.ini with scripts 3.4.4

read bhs.txt

---

---

Subject: Re: How do you Change nod and gdi color text ?  
Posted by [DeathC200](#) on Thu, 26 Feb 2009 01:09:59 GMT  
[View Forum Message](#) <> [Reply to Message](#)

which part of the hud.ini am i gonna need to look for to change the text color of them if you could post a screenshot that would help gratley for the part of changing the text color

---

---

Subject: Re: How do you Change nod and gdi color text ?  
Posted by [Gen\\_Blacky](#) on Thu, 26 Feb 2009 01:36:15 GMT  
[View Forum Message](#) <> [Reply to Message](#)

make a hud.ini in your data folder then change these settings

Quote:There is new code that lets you change the color used for the teams (i.e. red for nod and yellow for gdi)

You can also change the public and private message colors.

Note that the hud.ini file is parsed on the server too (for the colored message send commands and the get color engine calls).

This requires bhs.dll on the client.

You create a hud.ini file that looks something like this

[General]  
NodHouseRed=255  
NodHouseGreen=0  
NodHouseBlue=0  
GDIHouseRed=255  
GDIHouseGreen=204  
GDIHouseBlue=0  
PrivateMessageRed=0  
PrivateMessageGreen=0

PrivateMessageBlue=255  
PublicMessageRed=255  
PublicMessageGreen=255  
PublicMessageBlue=255

---

---

Subject: Re: How do you Change nod and gdi color text ?  
Posted by [Good-One-Driver](#) on Thu, 26 Feb 2009 01:48:41 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Like this?

Register on [jelly-server.com](http://jelly-server.com) then check this thread -  
<http://jelly-server.com/nuke/modules.php?name=FUDForums&file=index&t=msg&th=6367&start=0&S=a2438ee3931fb3c73dbaae1cd833f379>

#### File Attachments

1) [3.jpg](#), downloaded 512 times



Subject: Re: How do you Change nod and gdi color text ?  
Posted by [\\_SSnipe\\_](#) on Thu, 26 Feb 2009 03:29:03 GMT  
[View Forum Message](#) [Reply to Message](#)

[View Forum Message](#) <> [Reply to Message](#)

---

Gen\_Blacky wrote on Wed, 25 February 2009 17:36 make a hud.ini in your data folder then change these settings

Quote:There is new code that lets you change the color used for the teams (i.e. red for nod and yellow for gdi)

You can also change the public and private message colors.

Note that the hud.ini file is parsed on the server too (for the colored message send commands and the get color engine calls).

This requires bhs.dll on the client.

You create a hud.ini file that looks something like this

```
[General]
NodHouseRed=255
NodHouseGreen=0
NodHouseBlue=0
GDIHouseRed=255
GDIHouseGreen=204
GDIHouseBlue=0
PrivateMessageRed=0
PrivateMessageGreen=0
PrivateMessageBlue=255
PublicMessageRed=255
PublicMessageGreen=255
PublicMessageBlue=255
```

hes right

---

---

Subject: Re: How do you Change nod and gdi color text ?

Posted by [DeathC200](#) on Thu, 26 Feb 2009 03:45:46 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

ok but my specific colors are green for nod and orange for gdi

---

---

Subject: Re: How do you Change nod and gdi color text ?

Posted by [\\_SSnipe\\_](#) on Thu, 26 Feb 2009 04:05:22 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

use paint to get color values if you dont know how ask and ill post picture

---

---

Subject: Re: How do you Change nod and gdi color text ?

Posted by [DeathC200](#) on Thu, 26 Feb 2009 04:38:55 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

how do i get the color values i know it may seem stupid but i am learning alot of new stuff this week

---

---

Subject: Re: How do you Change nod and gdi color text ?

Posted by [\\_SSnipe\\_](#) on Thu, 26 Feb 2009 04:41:37 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

DeathC200 wrote on Wed, 25 February 2009 20:38how do i get the color values i know it may seem stupid but i am learning alot of new stuff this week

---

---

Subject: Re: How do you Change nod and gdi color text ?  
Posted by [DeathC200](#) on Thu, 26 Feb 2009 04:49:16 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

thanks this well help gratfully

---