
Subject: BrenBot/Renguard
Posted by [WINDEX](#) on Sun, 13 Jun 2010 15:23:20 GMT
[View Forum Message](#) <> [Reply to Message](#)

Ok there has to be a way to turn off renguard through brenbot instead of half mode

Subject: Re: BrenBot/Renguard
Posted by [ExEric3](#) on Sun, 13 Jun 2010 18:21:35 GMT
[View Forum Message](#) <> [Reply to Message](#)

I think its in wrong section. It should be WIN32.

Subject: Re: BrenBot/Renguard
Posted by [zunnie](#) on Mon, 09 May 2011 12:04:58 GMT
[View Forum Message](#) <> [Reply to Message](#)

#renguard.cfg

#--RenGuard Configuration File - Main Settings-----

Enable pure mode to only allow players with no custom textures and models to join
Pure_Mode = 0

How long to wait before kicking non-RG users after their warning message when
half-RG mode is off.
kicktimer = 30000

Enables and disables Half-RenGuard mode, which allows non-RenGuard users to play on
your server without being kicked, although they may not be able to use some commands.
halfrenguard = 1

Controls how many votes are required to forceRG someone.
forcerg_votes_required = 50

#--Settings for non-RG users-----

Allow non-RG users to recieve recommendations. 1 to allow, 0 to disallow
norg_allow_recommendations = 1

Allow non-RG users to receive automatic recommendations, for destroying buildings,
getting most kills in a round etc. 1 to allow, 0 to disallow
norg_allow_auto_recommendations = 1

Allow non-RG users to start votes. 1 to allow, 0 to disallow
norg_allow_start_vote = 1

Allow non-RG users to vote in votes. 1 to allow, 0 to disallow
norg_allow_vote = 1

#--Messages-----

How to notify non-RG users. Can be set to any of the following: msg, page, off.
Be aware that page only works for WOL users, so you should not rely on this.
If bhs.dll is installed this setting will be over-ridden with pamsg.
notify = off

Turns the RG kick message on or off. Set to 1 to enable it, 0 to disable.
nokickmsg = 0

Message to send players when they join without RenGuard, and half-RG mode is off
warnmessage = You need RenGuard to play on this server. Download it from www.renguard.com

How often to send a message to non-RG users, in seconds. Set to 0 to disable.
halfrenguard_pamsg_norg_interval = 0

Message to send to non-RG users. BHS.dll servers only.
halfrenguard_pamsg_norg = Running RenGuard on this Server is recommended. Download it
from www.renguard.com. With RenGuard, you will get unofficial patches ("core patches") and you
can use commands on this server!

How often to send the public chat message advising users that a player is not
using RG, in seconds. Set to 0 to disable.
halfrenguard_hostmsg_interval = 0

Public chat message to send advising users that a player is not using RG.
%name is replaced with the players name.
halfrenguard_hostmsg_message = %name is NOT running RenGuard, and COULD be cheating.

Your Message of the Day id, as given to you on the Server Motd Configuration at
www.renguard.com
Leave as 0 if you do not have an motd.
motd = 0

#--Other Settings-----

This setting is reserved for servers that have more than 1 external ip-address. It
lets you choose to which ip-address renguard is binding.
If you are having trouble connecting to renguard, set this to the same ip-address as
the ip from which you are hosting your server. This setting is optional.
bind_ip = 123.123.123.123
